Massachusetts State Police Crime Laboratory

Arson & Explosives Unit Information Paper



To provide general guidelines
for submitting agencies on the
submission of Arson and
Explosives related evidence to
the Massachusetts State Police
Crime Laboratory

Evidence Control Unit

Massachusetts State Police Crime Laboratory 59 Horse Pond Rd. Sudbury, MA 01776

Phone: 508-358-3155 Fax: 508-358-3222 Excellence in Service Through Quality Forensic Science

Massachusetts State Police Crime Laboratory ECU Arson & Explosives Unit Information Paper Issued By: Laboratory Director Issue Date: August 01, 2018 ID: 2700 Revision: 2

Page 1 of 2

Evidence submitted by external agencies for analysis by the Arson & Explosives Unit will only be accepted at the State Police Crime Laboratory Evidence Unit located at 59 Horse Pond Rd. in Sudbury

Contact Information

For Scene Response

GHQ

508-820-2121

Technical Questions

Arson & Explosives Unit

508-358-3110

Or

508-358-3100

Evidence Submission Appointments

508-358-3155

Explosives Devices

ALL Explosive Devices / IED's must be rendered safe by a Bomb Squad prior to submission to the Evidence Control Unit.



Packaging Requirements

Fire Debris

- Clean metal cans, free
 of rust and dents, all
 sealed airtight and
 labeled at scene.
 Cans should be taped
 over the edges in a
 criss-cross fashion to
 ensure the integrity of
 the sample. The tape
 is to be initialed and
 dated by the
 investigator.
- Glass vials should be used for raw liquid samples (These can be obtained from the laboratory if necessary). These should also be sealed using tape over the cap. The tape is to be initialed and dated by the investigator.

Explosive Debris

- Clean manila envelopes, static free bags, paper bags and/or clean metal cans, sealed and labeled at the scene. The packaging should be sealed, initialed and dated to ensure the integrity of the sample.
- Control samples (i.e., soil and debris recovered away from the blast site) should be packaged in a similar fashion.
- Chemical Reaction
 Bombs (CRB'S) are to
 be individually packaged in heat sealed plastic
 bags and entered into
 LIMS as separate items.

Gun Shot Residue

- Adhesive stubs taken from a sealed GSR Kit (example, Gunshot Residue Trace Evidence Kit from Tri-Tech) must have the questionnaire form filled out completely and sealed inside the kit.
- One stub for each hand is preferred.
- Sampling of hands must be completed within 4 hours of the incident.
- Sampling on Suicides will only be examined with prior approval from the Trace/Arson and Explosives Unit Supervisor.
- Clothing may be recovered at the scene and packaged in paper bags for further examination by a criminalist at the laboratory.

Number of Samples

Limit number of samples. Raw Liquids must be limited to one ounce sample or smaller.





Example of bottles and cans that can be used to submit Arson Evidence



ID: 2700 Revision: 2

Page 2 of 2